

DeltaLog10 release notes

Revision Number	Date	Notes
1.1.0.8	02/04/2024	Added indication of CLO and MET values in PMV column header in logged data table view (excluding HD32.1). Added possibility to import CLO and MET values stored in the data file, in microclimate indexes analysis (excluding HD32.1).
1.1.0.7	22/02/2024	Optimized export in CSV of large size files.
1.1.0.6	22/11/2023	Cumulative update that includes updated components and corrections in the "Discomfort Analysis" module. Added Visual C++ redistributable 2013 installation
1.1.0.4	30/05/2023	Added printing of the report for "Discomfort" in moderate environments according to the ISO7730 standard.
1.1.0.2	25/10/2022	Calculation correction in "Cold environments" module.
1.1.0.1	30/09/2022	Improved the connection with the instruments.
1.1.0.0	12/07/2022	General review.
1.0.1.7	14/02/2022	Added CP210x_VCP USB drivers necessary for HD32.1 manufactured from 02/2022.
	18/02/2020	Added compatibility for HD32.3TC.
1.0.1.6	11/09/2019	WBGT lim visualization according to new revision of ISO7243 standard.
1.0.1.5	22/05/2019	Changed default installation folder.
1.0.1.4	30/01/2019	HD21ABE17 monitor bug fixing.
1.0.1.3	20/12/2018	Bugs fixing.
1.0.1.2	13/11/2018	Regenerated setup file.
1.0.1.1	09/11/2018	Added new functionalities to comply with ISO7243:2017 standard. Corrected a calculation inaccuracy of the ISO7933 PHS index.



Revision Number	Date	Notes
0.1.6.7	17/10/2018	Added setting of CAV parameter for WBGT correction according to ISO 7243:2017 standard.

Members of GHM GROUP: GREISINGER | HONSBERG | Martens | IMTRON | Deltacim | VAL.CO